


Quick guide on making EOS 3 work under WinXp with limited user account


- System administrator installs EOS under his account.
- After the successful installation, go to the folder where you installed EOS (The default folder is C:\Compucon)
- Right-click on installation folder → Sharing and Security



- Go to "Security" tab and choose your limited account's username and grant him with Full Control rights.



- In case that "Security" tab doesn't appear go to Tools → Folder Options → "View" tab → Uncheck "Use simple file sharing"





- Your limited account now has the necessary privileges to execute EOS and access the database.